

PTV **MAP&GUIDE**

the mind of movement

PTV MAP&GUIDE INTRANET 2018

SYSTEM REQUIREMENTS

MULTI-SERVER INSTALLATION

PTV Map&Guide intranet 2018 - Multi-server installation

This document describes the system requirements and basic prerequisites that must be met before installation.

Note: We recommend installation on 2 servers for up to 25 users.

Mapserver (IIS, PTV xLocate Server, PTV xMap Server, map)

- ▶ Operating system: At least Windows Server 2008 R2 or newer

Note: Please remember that it must be at least the Standard Edition of Microsoft® Windows Server.

The following operating systems are not supported:

- Microsoft® Windows Server Essentials
 - Microsoft® Windows Small Business Server
 - Microsoft® Windows Server Web Editions
-

- ▶ Free RAM: at least 4 GB
- ▶ Free disc space: at least 20 GB
- ▶ CPU: x86 with at least 1 GHz, 4 processor cores
- ▶ Firewall: If the firewall is active, enable port 52822 and 80

Webserver

- ▶ Operating system: At least Windows Server 2008 R2 or newer
- ▶ Free RAM: 8 GB
- ▶ Free disc space: 40 GB
- ▶ CPU :X86 with at least 1 GHz, 6 or more processor cores
- ▶ Firewall: No port enable required
- ▶ Proxy server: If the proxy server is active, have the data ready for input during installation to access the following web services:
 - ▶ Traffic information <http://ti.ptvgroup.com>
 - ▶ Toll updates <http://lds.ptvgroup.com>
 - ▶ Exchange rates <http://www.ecb.europa.eu>
 - ▶ Freight exchange <https://connect.wktransportservices.com>
 - ▶ Truck Parking Europe <https://app.truckparkingeurope.com>
 - ▶ PTV Navigator <https://navigatordownload.ptvgroup.com/navigation-backend-service>
 - ▶ PTV Drive & Arrive <https://driveandarrive-v1.cloud.ptvgroup.com>
 - ▶ PTV Map&Guide intranet FAQ <https://www.ptvgroup.com/en/contact-support/ptv-mapandguide/>



the mind of movement

PTV GROUP

Haid-und-Neu-Str. 15
76131 Karlsruhe
Germany

www.ptvgroup.com